


Konica Minolta Bizhub series: Loading Windows Print Driver


1. Select <https://onyxweb.mykonicaminolta.com/OneStopProductSupport?appMode=Public&appMode=Public>
2. Search for the printer model, then click Drivers.
3. Select and download the driver based on the computer's operating system. If unsure, go to the start menu and search "about this PC."



4. Select the downloaded file. Open the zip file and press Drivers then Setup x64 to extract. Open Drivers and press Setup x64 again.
5. Follow the steps in the wizard. If the machine automatically finds the IP address, finish the installation. If it does not, continue onto the next steps.

Name	Size	Packed Size	Modified
Bmp	429 548	24 725	2018-04-19 10:20
Drivers	79 447 305	62 592 376	2018-04-19 10:23
Lang	529 114	176 626	2018-04-19 10:24
Readme	116 646	33 104	2018-04-19 10:24
setupsub	349 888	166 224	2018-04-19 10:24
Setup.exe	1 034 488	430 476	2018-02-13 18:32
Setup.ini	1 747	543	2018-03-19 18:13
Setup64.exe	1 437 432	530 245	2018-02-13 18:32


6. Close out of the wizard. Select the Windows start menu and type in "Printers & Scanners" to open.
7. Select + to add the printer.
8. Select "The printer I want isn't listed."
9. Select "Add a printer using a TCP/IP address or hostname" and press Next.



10. From the drop down, choose TCP/IP Device.

11. Enter the machine's IP address, uncheck the Query button, and press Next.

- If not sure of the IP address, go to the printer. Select Menu >> Utility >> Device Information for the IPv4 address.



Type a printer hostname or IP address

Device type: **TCP/IP Device**


Hostname or IP address: **10.0.1.199**

Port name: **10.0.1.199_1**

Query the printer and automatically select the driver to use





- 12. Select Have Disk.
- 13. Select Browse.
- 14. Select the drop down and go to the Downloads folder.
- 15. Select the file of the printer.
- 16. Select Driver >> Drivers.
- 17. Select PCL then EN .
- 18. Select Win_x64 and click the 1 option. Press OK.
- 19. Select the option that is closest to the printer model. Ex: a Bizhub C308 would select C368 series. Press Next.
- 20. Name the printer and press Next.
- 21. Select "Do not share this printer" and press Next.
- 22. Select "Print a test page" and press Finish.



Install the printer driver

Choose your printer from the list. Click Windows Update to see more models.
To install the driver from an installation CD, click Have Disk.



****Note:** Print drivers are set to 2-sided and color printing by default. For assistance on changing defaults, please contact the Loffler service department. Contact information is on the red sticker on the front of the machine. Please refer to your 5-6 digit ID number when contacting.

